
# Configuration steps for TensorFlow object detection-

## STEP-1 Download the following content-


- 1. Download v1.13.0 model.
- Download the ssd\_mobilenet\_v1\_coco model from the model zoo or any other model of your choice from TensorFlow 1 Detection Model Zoo.
- 3. Download Dataset & utils.
- 4. Download labelimg tool for labeling images.

before extraction, you should have the following compressed files -




# STEP-2 Extract all the above zip files into a tfod folder and remove the compressed files-

Now you should have the following folders -



## STEP-3 Creating virtual env using conda-



## STEP-4 Install the following packages in your new environment-

#### for GPU

pip install pillow lxml Cython contextlib2 jupyter matplotlib pandas opencv-python tensorflow-gpu==1.15.0  $\,$ 

### for CPU only

pip install pillow lxml Cython contextlib2 jupyter matplotlib pandas opencv-python tensorflow==1.15.0

### STEP-5 Install protobuf using conda package manager-

conda install -c anaconda protobuf

## STEP-6 For protobuff to .py conversion download from a tool from here-

For windows -> download source for other versions and OS - click here

Open command prompt and cd to research folder.

Now in the research folder run the following command-

#### For Linux or Mac


protoc object\_detection/protos/\*.proto --python\_out=.

#### For Windows

protoc object\_detection/protos/\*.proto --python\_out=.

### STEP-7 Paste all content present in utils into research folder-

Following are the files and folder present in the utils folder-



## STEP-8 Paste ssd\_mobilenet\_v1\_coco or any other model downloaded from model zoo into research folder-

Now cd to the research folder and run the following python file-

```
python xml_to_csv.py
```

### STEP-9 Run the following to generate train and test records-

from the research folder-

```
python generate_tfrecord.py --csv_input=images/train_labels.csv --
image_dir=images/train --output_path=train.record

python generate_tfrecord.py --csv_input=images/test_labels.csv --
image_dir=images/test --output_path=test.record
```

### STEP-10 Copy from

research/object\_detection/samples/config/ YOURMODEL.config file into research/training-



The following config file shown here is with respect to **ssd\_mobilenet\_v1\_coco**. So if you have downloaded it for any other model apart from SSD you'll see config file with YOUR\_MODEL\_NAME as shown below-

```
model {
YOUR_MODEL_NAME {
  num_classes: 6
  box_coder {
    faster_rcnn_box_coder {
```

Hence always verify YOUR\_MODEL\_NAME before using the config file.

STEP-11 Update *num\_classes, fine\_tune\_checkpoint* ,and *num\_steps* plus update *input\_path* and *label\_map\_path* for both *train\_input\_reader* and *eval\_input\_reader*-



#### Info

Changes to be made in the config file are highlighted in yellow color. You must update the value of those keys in the config file.

#### Click here to see the full config file # SSDLite with Mobilenet v1 configuration for MSCOCO Dataset. 2 # Users should configure the fine\_tune\_checkpoint field in the train 3 config as 4 # well as the label\_map\_path and input\_path fields in the train\_input\_reader and # eval\_input\_reader. Search for "PATH\_TO\_BE\_CONFIGURED" to find the 6 fields that # should be configured. 8 9 10 model { 11 ssd { 12 num\_classes: 6 13 box\_coder { faster\_rcnn\_box\_coder { 14 y\_scale: 10.0 15 x\_scale: 10.0 16 height\_scale: 5.0 17 18 width\_scale: 5.0 19 20 21 matcher { 22 argmax\_matcher { 23 matched\_threshold: 0.5 24 unmatched\_threshold: 0.5 25 ignore\_thresholds: false 26 negatives\_lower\_than\_unmatched: true 27 force\_match\_for\_each\_row: true 28 } 29 30 similarity\_calculator { 31 iou\_similarity { 32 } 33 34 anchor\_generator { ssd\_anchor\_generator { 35 36 num\_layers: 6 37 min\_scale: 0.2 max\_scale: 0.95 38 39 aspect\_ratios: 1.0 aspect\_ratios: 2.0 40 41 aspect\_ratios: 0.5 aspect\_ratios: 3.0 42 43 aspect\_ratios: 0.3333 44 45 46 image\_resizer { 47 fixed\_shape\_resizer { 48 height: 300 49 width: 300 50 51 box\_predictor { 52 53 convolutional\_box\_predictor { min\_depth: 0 54 55 max\_depth: 0 56 num\_layers\_before\_predictor: 0 57 use\_dropout: false


```
dropout_keep_probability: 0.8
 58
 59
              kernel_size: 3
 60
              use_depthwise: true
 61
              box_code_size: 4
 62
              apply_sigmoid_to_scores: false
 63
              conv_hyperparams {
 64
                 activation: RELU_6,
 65
                 regularizer {
 66
                   12_regularizer {
 67
                     weight: 0.00004
 68
 69
 70
                 initializer {
 71
                  truncated_normal_initializer {
 72
                    stddev: 0.03
 73
                    mean: 0.0
 74
 75
 76
                batch_norm {
 77
                  train: true,
 78
                   scale: true,
 79
                   center: true,
 80
                   decay: 0.9997,
 81
                  epsilon: 0.001,
 82
 83
              }
 84
 85
 86
          feature_extractor {
 87
            type: 'ssd_mobilenet_v1'
 88
            min_depth: 16
 89
            depth_multiplier: 1.0
            use_depthwise: true
 90
 91
            conv_hyperparams {
 92
              activation: RELU_6,
 93
              regularizer {
 94
                12_regularizer {
 95
                   weight: 0.00004
 96
 97
 98
              initializer {
 99
                truncated_normal_initializer {
100
                   stddev: 0.03
                   mean: 0.0
101
102
103
104
              batch_norm {
105
                train: true,
106
                scale: true,
107
                center: true,
108
                decay: 0.9997,
109
                 epsilon: 0.001,
110
111
112
113
          loss {
114
            classification_loss {
115
              weighted_sigmoid {
116
117
118
            localization_loss {
```

```
119
              weighted_smooth_l1 {
120
121
122
            hard_example_miner {
123
              num_hard_examples: 3000
124
              iou_threshold: 0.99
125
              loss_type: CLASSIFICATION
126
              max_negatives_per_positive: 3
127
              min_negatives_per_image: 0
128
129
            classification_weight: 1.0
130
            localization_weight: 1.0
131
132
          normalize_loss_by_num_matches: true
133
          post_processing {
134
            batch_non_max_suppression {
              score_threshold: 1e-8
135
              iou_threshold: 0.6
136
137
              max_detections_per_class: 100
138
              max_total_detections: 100
139
140
            score_converter: SIGMOID
141
142
        }
143
      }
144
145
      train_config: {
146
        batch_size: 24
147
        optimizer {
148
          rms_prop_optimizer: {
149
            learning_rate: {
150
              exponential_decay_learning_rate {
151
                initial_learning_rate: 0.004
                decay_steps: 800720
152
153
                decay_factor: 0.95
154
155
156
            momentum_optimizer_value: 0.9
157
            decay: 0.9
158
            epsilon: 1.0
159
160
        fine_tune_checkpoint: "ssd_mobilenet_v1_coco_2018_01_28/model.ckpt"
161
162
        from_detection_checkpoint: true
163
        # Note: The below line limits the training process to 200K steps, which
164
      we
165
        # empirically found to be sufficient enough to train the pets dataset.
166
      This
167
        # effectively bypasses the learning rate schedule (the learning rate
168
      will
169
       # never decay). Remove the below line to train indefinitely.
170
        num_steps: 20000
171
        data_augmentation_options {
172
          random_horizontal_flip {
173
174
175
        data_augmentation_options {
176
          ssd_random_crop {
177
178
179
```

```
180
181
      train_input_reader: {
182
        tf_record_input_reader {
          input_path: "train.record
183
184
        label_map_path: "training/labelmap.pbtxt
185
186
187
188
      eval_config: {
189
       num_examples: 8000
190
        \# Note: The below line limits the evaluation process to 10 evaluations.
191
       # Remove the below line to evaluate indefinitely.
192
       max_evals: 10
193
194
195
      eval_input_reader: {
196
      tf_record_input_reader {
          input_path: "test.record"
        label_map_path: "training/labelmap.pbtxt
        shuffle: false
        num_readers: 1
```


## STEP-12 From *research/object\_detection/legacy/* copy *train.py* to research folder

legacy folder contains train.py as shown below -



## STEP-13 Copy *deployment* and *nets* folder from *research/slim* into the *research* folder-

slim folder contains the following folders -



STEP-14 NOW Run the following command from the *research* folder. This will start the training in your *local system*-



copy the command and replace **YOUR\_MODEL.config** with your own model's name for example **ssd\_mobilenet\_v1\_coco.config** and then run it in cmd prompt or terminal. And *make sure you* are in research folder.

python train.py --logtostderr --train\_dir=training/ -pipeline\_config\_path=training/YOUR\_MODEL.config



#### Warning

Always run all the commands in the research folder.